

Add a Provider

Providers can be added by an admin or by the user. Any providers you add you can edit by clicking Edit in the Actions menu. You can also Delete any providers you add.

Provider Types

Transformable.app includes the following provider types for integration with deployment providers and self hosted applications.

Laravel Forge Provider

transformable.app uses the Forge provider to deploy your rootless Docker servers and configure Portainer on it. Recipes allow us to run scheduled tasks on your servers. These managed maintenance tasks and our human in the loop approach assure you can count on your cloud daily.

Just the Forge API Key is required, a provider is created automatically when you register with your API key.

Beszel Provider

transformable.app will always assign a Beszel Provider to your account. This assures a Beszel Agent is installed on every server you deploy so both you and our team can monitor and get alerted of the server resources. These include: disk space, memory, cpu, load averages and network activity.

You can also install the Beszel Hub app from the Apps Library and run your own hub.

Beszel Provider Required Fields

- Beszel Host - ex. hub.formable.app
- Beszel Email - Beszel login email for Beszel Agent deployments.
- Beszel Password - Beszel login password for Beszel Agent deployments.
- Beszel Public Key - Click Add System in Beszel to get the public key for automated Beszel Agent deployments.

Homarr Provider

You can add a Homarr Provider after installing Homarr from the Apps Library on one of your servers and creating an API key. Once a Homarr Provider is configured, any deployed apps are added with a link and icon to the available apps in Homarr. Allowing you to easily create dashboards of apps quickly.

Homarr Provider Required Fields

- Homarr Host - ex. dash.formable.app
- Homarr API Key - Create an API key in Homarr

NTFY Provider

You can add a NTFY Provider in addition to the one used by transformable.app to receive notifications when any Alerts are issued. This is an optional notification channel that can be used along with the default Email notifications.

NTFY Provider Required Fields

- NTFY Host - ex. notify.formable.app
- NTFY Channel - ex. mychannel12345
- NTFY Username
- NTFY Password

Uptime Kuma Provider

You can add an Uptime Kuma Provider in addition to the one used by transformable.app to monitor the sites and SSL certificates of your Apps. A monitor is created in Uptime Kuma when an App is deployed in transformable.app with a site.

Uptime Kuma Provider Required Fields

- Uptime Kuma API Host - ex. uptime-api.formable.app
- Uptime Kuma Username
- Uptime Kuma Password

Revision #2

Created 2026-02-01 00:45:25 UTC by Nick S

Updated 2026-02-01 00:47:16 UTC by Nick S